




Event File Erasure Protocol Filter Exec


If you run a protocol filter and accidentally put the same name for the “source file” and the “result file”, a dialog box appears with the message “Source and Result Identical”. It seems to be good, but the system will erase the source file (ace).





There's a workaround:-

Don't close the box dialog.
 Open c:\Clarinet\Clatool
 Sort by "Date modified" – Erase the WAC_FXLL.aci file.



Return to the Clarinet - Protocol Filter Exec (it was left open).
 Close the dialog box "Source and Result Identical" BUT don't click OK, click on the red cross (to cancel).
 Put the good name of "result file".
 Click to Apply.

